## Get Remmina and Vino (VNC Server) to work together

**Problem:** Vino by default requires TLS authentication in order to encrypt the password. Remmina on the other hand does not support that. The only common method is plaintext passwords.

**Solution:** quite simple actually, we need to disable encryption on the server side:

sudo apt-get -y install dconf-tools
dconf write /org/gnome/desktop/remote-access/require-encryption false
/usr/lib/vino/vino-server --sm-disable start

**A word of caution:** Now before you do this, be aware, that after following these steps, the vnc password travel through the network in clear text. not something you should do in an untrusted network (yes, the internet for example). I recommend using an ssh tunnel for your vnc connections over such networks.

in order to enforce using an ssh tunnel you could run

gsettings set org.gnome.Vino network-interface lo

this only allows connections from the localhost and therefore forces external pc's to use an ssh tunnel.

in your remmina settings' ssh tab enable ssh tunnel and also enable the tunnel via loopback address option.

From:

http://wiki.psuter.ch/ - pswiki

Permanent link:

http://wiki.psuter.ch/doku.php?id=get\_vino\_and\_remmina\_to\_work\_together

Last update: **11.10.2015 08:56** 

