Disabling the NVIDIA Nouveau driver in Ubuntu

sometimes you might want to use the most current nvidia binary driver rather than the nouveau driver package.. or you want no driver at all for whatever reason, so you need to disable the pre-installed nouveau driver..

note all commands below should be executed with root privileges, either prepend sudo or become root first by running sudo su -

edit /etc/modprobe.d/blacklist-framebuffer.conf

make sure these two lines are in there:

blacklist nouveau blacklist nvidiafb

now uninstall the driver

sudo apt-get --purge remove xserver-xorg-video-nouveau

also recreate the initrd image as newer ubuntu releases load the nouveau module in there already.

update-initramfs -u

and reboot

after the reboot there should not be any nouveau related modules anymore. try

lsmod | grep nouveau

if it returns an empty result, you where successful:) if not, try adding these parameters in the file /etc/default/grub to the GRUB_CMDLINE_LINUX_DEFAULT parameter:

rdblacklist=nouveau nouveau.modeset=0

after that, you need to recreate the grub config by running

update-grub

and reboot once more. check again and if you still see nouveau modules, start googling;) so far these steps have always worked on all ubuntu systems i had touched since 10.04

use a repository for a packaged driver

if you want to install the nvidia driver instead of the nouveau driver, you can probably save the above

steps if you are happy with the "proprietary drivers" provided through ubuntu. however, these drivers might be rather old. if you need newer drivers, you can use a repository which provides them. and if you need to auto-install the latest nvidia driver, you can use a python utility to detect which driver package you need. Here is how this is done:

```
# install python pip to get pyvidia
apt-get -y install python-pip
pip install --upgrade pip
pip install pyvidia
pip install six
add-apt-repository -y ppa:graphics-drivers/ppa
apt-get -y update
apt-get -y install nvidia-$(pyvidia)
```

what if nouveau is disabled, nvidia is installed but xorg logs "no device found"?

if you have a system that contains both nvidia and non-nvidia graphics adapters (for example an onboard intel GPU), you might need to tell xorg which PCI device to use in combination with the nvidia driver. to do that, run

```
nvidia-smi
```

on the target system. it will display a Bus-Id for your card that looks similar to this:

```
0000:01:00.0
```

you will need this id for your xorg.conf file. However, the values displayed through nvidia-smi are \mathbf{hex} values, for xorg.conf you need $\mathbf{decimal}$ numbers. if you don't know how to convert from hex to dec you can just google for "0x31 = ? decimal" and it will show you the decimal conversion as a suggested result:) we are only interested in the 01:00.0 section, you can ignore the 0000: at the begining. now edit your /etc/X11/xorg.conf file and find the Device Section. in this section add a BusID parameter so that the entire section looks something like this:

```
Section "Device"

Identifier "Device0"

Driver "nvidia"

BusID "PCI:1:0:0"

EndSection
```

there might be more stuff in there, that's fine, just add the BusID line and keep the rest as is. what's important is, that you add the BusID in the Device section where the Driver is set to "nvidia":)

now restart your xorg and it should find your card at the given PCI id

http://wiki.psuter.ch/ Printed on 19.12.2025 11:03

From:

http://wiki.psuter.ch/ - **pswiki**

Permanent link:

http://wiki.psuter.ch/doku.php?id=disable_nvidia_nouveau&rev=1480584530

Last update: **01.12.2016 10:28**

